


Automated Unit Test Suite (Details)




More Details

- File I/O details and options
- Manipulating buffer sizes
 - Depends on the protocols you use
- Understanding the *two* HDL assemblies used for testing
 - When to use each one (simulators vs. hardware)
 - Configuration options
- Debugging your failed tests
 - "Where did my overnight simulation go?"
- More implementation details




file_read.rcc/.hdl Basics


- Implements the ocpi.core/components/specs/file_read-spec.xml
- No Protocol (opcode default is zero)
- **fileName** path limit is 1024 char
- Two modes of operation
 - Data Streaming – Contents of file simply copied to payload of a stream of messages
 - Fixed number of bytes of data **messageSize** (upcoming slides) defaults to 4KB
 - All with the same opcode
 - Messaging – Contents of file are interpreted as a sequence of defined messages
 - 8-byte header precedes payload data of each message
 - Four byte length (in bytes, little-endian), one byte opcode, three padding bytes
 - **MessagesInFile**="true" (default "false") and **overrides messageSize**
- **repeat** default is false, restart reading at the beginning of file
- Produces a ZLM after last data is read



file_write.rcc/.hdl Basics

- Implements the `ocpi.core/components/specs/file_write-spec.xml`
- No Protocol (opcode default is zero)
- ***fileName*** path limit is 1024 char
- Two modes of operation
 - Data Streaming – Contents of file becomes the payloads of a stream of messages, no message lengths or opcodes are recorded.
 - Messaging – Contents of the output file is written as a sequence of defined messages
 - 8-byte header precedes payload data of each message
 - Four byte length (in bytes, little-endian), one byte opcode, three padding bytes
 - ***messagesInFile***="true" (default "false")
- "Done" upon detection of a ZLM after last data is read





File Read/Write's *messagesInFile*

- If more than one opcode is needed, use `messagesInFile`
- Input data needs to have:
 - Length of message (in Bytes)
 - Opcode Number to transmit
 - Message (if non-zero length)
- Example with 4 Operations:

2	0	short scalar mesg.	4	1	short sequence(0) mesg.	short sequence(1) mesg.	4	2	long scalar mesg.	1	3	char scalar mesg.
---	---	--------------------------	---	---	-------------------------------	-------------------------------	---	---	-------------------------	---	---	-------------------------

File Read *messageSize*



- In general, bigger the buffer, higher the throughput
- Determine a *messageSize* that best utilizes the protocol buffer size
 - Protocol buffer size is the largest of all the operations in a protocol
 - This is needed because `file_read` doesn't "know" the protocol within
- How to calculate the protocol buffer size?
 - Protocol buffer size = max operation size × *length* of the max operation size
 - max operation size - the operation in the protocol with largest number of bytes
 - *length* of the max operation size - either the `StringLength`, `SequenceLength`, `ArrayDimensions`, or size of the type

Protocol Buffer Size



protocol buffer size = max operation size × length of the max operation size

Example 1

<Protocol>

<Operation Name="demo">

<Argument Name="data" Type="Struct" SequenceLength="2048">

<Member Name="I" Type="Short"/>

<Member Name="Q" Type="Short"/>

</Argument>

</Operation>

</Protocol>

Protocol Buffer Size



protocol buffer size = max operation size × length of the max operation size

Example 1

<Protocol>

<Operation Name="demo">

<Argument Name="data" Type="Struct" SequenceLength="**2048**


<Member Name="I" Type="**Short**

<Member Name="Q" Type="**Short**

</Argument>

</Operation>

</Protocol>



Solution: Protocol Buffer Size is 4 Bytes x 2K = **8K Bytes**

Protocol Buffer Size

protocol buffer size = max operation size × length of the max operation size

Example 2


<Protocol>

 <Operation Name="demo">

 <Argument Name="data" Type="Short"></Argument>

 </Operation>

</Protocol>



Protocol Buffer Size



protocol buffer size = max operation size × length of the max operation size

Example 2


<Protocol>

<Operation Name="demo">

<Argument Name="data" Type="**Short**"></Argument>

</Operation>

</Protocol>



Solution: Protocol Buffer Size is 2 Bytes x 1 Scalar = **2 Bytes**

Protocol Buffer Size



protocol buffer size = max operation size × length of the max operation size

Example 2

<Protocol>

<Operation Name="demo1">

<Argument Name="data" Type="longlong" ArrayDimensions="2048"> </Argument>

</Operation>

<Operation Name="demo2">

<Argument Name="data" Type="Struct" SequenceLength="2048">

<Member Name="I" Type="Short"/>

<Member Name="Q" Type="Short"/>

</Argument>

</Operation>

</Protocol>

Protocol Buffer Size



protocol buffer size = max operation size × length of the max operation size

Example 2

<Protocol>

 <Operation Name="demo1">

 <Argument Name="data" Type="longlong" ArrayDimensions="2048"> </Argument>

 </Operation>

 <Operation Name="demo2">

 <Argument Name="data" Type="Struct" SequenceLength="2048">

 <Member Name="I" Type="Short"/>

 <Member Name="Q" Type="Short"/>

 </Argument>


 </Operation>

</Protocol>

Solution: Protocol Buffer Size is 8B x 2K = **16KB**, 4B x 2K = 8KB


Two HDL Test Assemblies

- Both built around "core" of
(data in) \Rightarrow metadata_stressor \Rightarrow UUT \Rightarrow backpressure \Rightarrow (data out)
- {component}.test/gen/assemblies/<component>_0/
 - Uses file I/O in an RCC worker
 - (data in) and (data out) above are the assembly's external ports
 - Can be built for *any* HDL platform
 - Including simulators ("co-simulation")
 - Uses the simulatable portions of the data plane
 - No DMA Engine
- {component}.test/gen/assemblies/<component>_0_frw/
 - Uses HDL file I/O workers
 - Can *only* be used on simulator platforms
 - Generally much faster simulations than co-simulation
 - (data in) and (data out) above are file_read.hdl and file_write.hdl



Data Flow Configurations

- Data flow as noted on previous slide:
(data in) \Rightarrow metadata_stressor \Rightarrow UUT \Rightarrow backpressure \Rightarrow (data out)
- By default "backpressure" is applied to ensure an HDL worker properly respects flow control on its output
 - Can be disabled via XML with "disableBackpressure"
- "metadata_stressor" can ensure worker's input properly handles intra-worker protocols and data starvation
 - Configured via XML with "stressorMode"
 - `bypass` – disabled (default configuration)
 - `throttle` – randomly holds back data (starvation)
 - `metadata` – manipulates metadata randomly (e.g. `som`) (edge conditions)
 - `full` – above two plus random idle cycles between messages (full compliance)




Unit Test Suite Debug

- Log files may be found at
run/<platform>/case##.##.<component>.<implementation>.log
- The ocpirun command that was executed may be found in the log file

```
$ OCPI_LIBRARY_PATH=../../lib/rcc:../../gen/assemblies:  
$OCPI_CDK_DIR/lib/components/rcc ocpirun -d -v -mcomplex_mixer=hdl  
-wcomplex_mixer=complex_mixer -Pcomplex_mixer=modelsim --sim-  
dir=case00.00.complex_mixer.hdl.simulation --dump-  
file=case00.00.complex_mixer.hdl.props  
-pfile_write=fileName=case00.00.complex_mixer.hdl.out.out  
../../gen/applications/case00.00.xml
```

- You can copy & paste (or modify) the above command, but it must be run from the run/<platform> directory



Unit Test Suite Simulation



- Execute the 'ocpiview' command from the <component>.test/ directory


```
$ ocpiview run/xsim/case###.##.<component>.simulation/ &
```

- The 'sim.out' simulator log file may be found at

```
run/xsim/case###.##.<component>.simulation/<component>_0_f  
rw.xsim.<datestamp>/sim.out
```


Peeking "Under the Hood"

- Advanced Usage Information
 - make targets for CLI usage
 - Directory layouts
 - Two examples of cases.xml
 - First is simple training example with Xilinx-provided cores
 - Second is ocpi.assets copy (complicated, CORDIC-based)



Make Targets (and GUI Buttons)

- From the project directory or component library directory

\$ make test Tests=<component>.test HdlPlatform=xsim **(Generate/Build)**

\$ make runtest Tests=<component>.test OnlyPlatforms=xsim View=1 **(Prepare/Run/Verify/View a specific test)**

\$ make runtest OnlyPlatforms=xsim View=1 **(Prepare/Run/Verify/View a ALL tests)**

- From the <component>.test/ directory

\$ make run OnlyPlatforms=xsim View=1 **(Prepare/Run/Verify/View)**

- Or from the <component>.test directory

\$ make HdlPlatform=xsim **(Generate/Build, where default is Build that depends on Generate)**

\$ make run OnlyPlatforms=xsim View=1 **(Prepare/Run/Verify/View, where Run means an interleaved Run/Verify that depends on Prepare)**

- Or from the <component>.test directory

\$ make generate OnlyPlatforms=xsim **(Generate)**


\$ make build OnlyPlatforms=xsim **(Build)**

\$ make prepare OnlyPlatforms=xsim **(Prepare)**

\$ make runonly OnlyPlatforms=xsim **(Run)**

\$ make verify OnlyPlatforms=xsim **(Verify)**

\$ make view OnlyPlatforms=xsim **(View)**



Make Targets (cont)



- From the project directory or component library directory

\$ make cleantest – clean all test results (removes the gen and run directories)

\$ make cleanrun – clean all run results (removes the run directory)

\$ make cleansim – clean all simulation output (removes the run/<simulator>/simulations directory)

- Or from the <component>.test directory

\$ make clean – clean all test results (removes the gen and run directories)

\$ make cleanrun – clean all run results (removes the run directory)

\$ make cleansim – clean all simulation output (removes the run/<simulator>/simulations directory)

Tree of complex_mixer.test/gen/ directory



```
$ tree -L 3 gen
```

```
gen
```


```
├── applications
│   ├── case00.00.xml
│   ├── case00.01.xml
│   ├── case00.02.xml
│   ├── case00.03.xml
│   └── verify_case00.sh
├── assemblies
│   ├── complex_mixer_0
│   │   ├── complex_mixer_0.xml
│   │   └── Makefile
│   ├── complex_mixer_0_frwr
│   │   ├── complex_mixer_0_frwr.xml
│   │   ├── container-complex_mixer_0_frwr_xsim_base
│   │   ├── container-complex_mixer_0_frwr_modelsim_base
│   │   ├── gen
│   │   ├── lib
│   │   ├── Makefile
│   │   ├── target-xsim
│   │   └── target-modelsim
│   └── Makefile
```

```
$ tree -L 3 gen (continued)
```

```
gen
```

```
├── cases.txt
├── cases.xml
├── cases.xml.deps
└── inputs
    ├── case00.00.in
    ├── case00.01.in
    ├── case00.02.in
    └── case00.03.in
```

Tree of complex_mixer.test/run/ directory



```
$ tree -L 3 run
```


```
run
├── centos7
│   ├── case00.00.complex_mixer.rcc.log
│   ├── case00.00.complex_mixer.rcc.out.out
│   ├── case00.00.complex_mixer.rcc.props
│   ├── case00.02.complex_mixer.rcc.log
│   ├── case00.02.complex_mixer.rcc.out.out
│   ├── case00.02.complex_mixer.rcc.props
│   └── run.sh
└── xsim
    ├── case00.00.complex_mixer.hdl.log
    ├── case00.00.complex_mixer.hdl.out.out
    ├── case00.00.complex_mixer.hdl.props
    ├── case00.00.complex_mixer.hdl.simulation
    │   └── complex_mixer_0_frw.xsim.20170512172244
    ├── case00.01.complex_mixer.hdl.log
    ├── case00.01.complex_mixer.hdl.out.out
    ├── case00.01.complex_mixer.hdl.props
    └── case00.01.complex_mixer.hdl.simulation
```

```
$ tree -L 3 run (continued)
```

```
run
├── complex_mixer_0_frw.xsim.20170512172303
│   ├── case00.02.complex_mixer.hdl.log
│   ├── case00.02.complex_mixer.hdl.out.out
│   ├── case00.02.complex_mixer.hdl.props
│   └── case00.02.complex_mixer.hdl.simulation
│       └── complex_mixer_0_frw.xsim.20170512172323
│           ├── case00.03.complex_mixer.hdl.log
│           ├── case00.03.complex_mixer.hdl.out.out
│           ├── case00.03.complex_mixer.hdl.props
│           └── case00.03.complex_mixer.hdl.simulation
│               └── complex_mixer_0_frw.xsim.20170512172342
└── run.sh

└── runtests.sh
```

complex_mixer cases.txt Example 1



Values common to all property combinations:

```
=====
ocpi_debug = false
ocpi_endian = little
phs_inc = -8192
```

Descriptions of the 1 case and its subcases:

```
=====
Case case00:
Summary of subcases
Subcase #  enable  data_select
-----  -
0:         false   false
1:         false   true
2:         true    false
3:         true    true
```

Subcase 00:

```
ocpi_debug = false
ocpi_endian = little
enable = false
phs_inc = -8192
data_select = false
```

Subcase 01:

```
ocpi_debug = false
ocpi_endian = little
enable = false
phs_inc = -8192
data_select = true
```

Subcase 02:

```
ocpi_debug = false
ocpi_endian = little
enable = true
phs_inc = -8192
data_select = false
```

Subcase 03:


```
ocpi_debug = false
ocpi_endian = little
enable = true
phs_inc = -8192
data_select = true
```

Unit Test Suite cases.xml Example 1



```
<cases spec='ocpi.training.complex_mixer'>
  <case name='case00'>
    <subcase id='0'>
      <worker name='complex_mixer' model='hdl' outputs='out'/>
      <worker name='complex_mixer' model='rcc' outputs='out'/>
    </subcase>
    <subcase id='1'>
      <worker name='complex_mixer' model='hdl' outputs='out'/>
    </subcase>
    <subcase id='2'>
      <worker name='complex_mixer' model='hdl' outputs='out'/>
      <worker name='complex_mixer' model='rcc' outputs='out'/>
    </subcase>
    <subcase id='3'>
      <worker name='complex_mixer' model='hdl' outputs='out'/>
    </subcase>
  </case>
</cases>
```

complex_mixer cases.txt Example 2



Values common to all property combinations:

```
=====
ocpi_debug = false
ocpi_endian = little
CHIPSCOPE_p = false (specific to worker complex_mixer.hdl)
CORDIC_STAGES_p = 16 (specific to worker complex_mixer.hdl)
PEAK_MONITOR_p = true (specific to worker complex_mixer.hdl)
phs_inc = -8192
phs_init = 0 (specific to worker complex_mixer.hdl)
mag = 1024 (specific to worker complex_mixer.hdl)
messageSize = 8192 (specific to worker complex_mixer.hdl)
```

Descriptions of the 1 case and its subcases:

=====

Case case00:

Summary of subcases

Subcase #	NCO_DATA_WIDTH_p	INPUT_DATA_WIDTH_p	enable	data_select
0:	12	12	false	false
1:				true
2:			true	false
3:				true
4:	16	16	false	false
5:				true
6:			true	false
7:				true

Subcase 00:

```
ocpi_debug = false
ocpi_endian = little
CHIPSCOPE_p = false
NCO_DATA_WIDTH_p = 12
INPUT_DATA_WIDTH_p = 12
CORDIC_STAGES_p = 16
PEAK_MONITOR_p = true
enable = false
phs_inc = -8192
phs_init = 0
mag = 1024
messageSize = 8192
data_select = false
```

Subcase 01:

```
ocpi_debug = false
ocpi_endian = little
CHIPSCOPE_p = false
NCO_DATA_WIDTH_p = 12
INPUT_DATA_WIDTH_p = 12
CORDIC_STAGES_p = 16
PEAK_MONITOR_p = true
enable = false
phs_inc = -8192
phs_init = 0
mag = 1024
messageSize = 8192
data_select = true
```


Unit Test Suite cases.xml Example 2



```
<cases spec='ocpi.assets.dsp_comps.complex_mixer'>
  <case name='case00'>
    <subcase id='0'>
      <worker name='complex_mixer' model='hdl' outputs='out'/>
      <worker name='complex_mixer' model='rcc' outputs='out'/>
    </subcase>
    <subcase id='1'>
      <worker name='complex_mixer' model='hdl' outputs='out'/>
    </subcase>
    <subcase id='2'>
      <worker name='complex_mixer' model='hdl' outputs='out'/>
      <worker name='complex_mixer' model='rcc' outputs='out'/>
    </subcase>
    <subcase id='3'>
      <worker name='complex_mixer' model='hdl' outputs='out'/>
    </subcase>
```

```
    <subcase id='4'>
      <worker name='complex_mixer-1' model='hdl' outputs='out'/>
    </subcase>
    <subcase id='5'>
      <worker name='complex_mixer-1' model='hdl' outputs='out'/>
    </subcase>
    <subcase id='6'>
      <worker name='complex_mixer-1' model='hdl' outputs='out'/>
    </subcase>
    <subcase id='7'>
      <worker name='complex_mixer-1' model='hdl' outputs='out'/>
    </subcase>
  </case>
</cases>
```